


ZCM6-APP PICO & Channel Pairing


1. Go to 'Setting' page and find the 'Channel Pairing' option

Settings → Module Settings → Channel Pairing




2. PICO Pairing


- 1) Click the "+" area, and a panel pairing window will pop up, prompting the user to press the same button on the panel twice. Any button on the PICO will be fine.



- 2) If you want to cancel the pairing, click 'Cancel' to cancel the pairing and return to the add page.




- 3) If the panel has been bound to another device, a pop-up window will appear too. Click OK to return to the add page.




- 4) After the panel is successfully paired, enter the channel pairing page.

3. Channel Pairing


- 1) Click the "Click" button and enter the "Select Load" page. The available options include all loads except the constant load.




- 2) Click the "Confirm" button, and then return to the panel information page, the corresponding load just selected will be displayed on the button.



- 3) After completing the load selection, click the "Confirm" button to send the command, and a window will pop up to prompt pairing successful.




- 4) After successful pairing, and the corresponding load on the button will be displayed in green.



4. Channel Clear

- 1) Click "Clear" to pop up a confirmation window. Click "Confirm" to clear the channel data.



5. Panel Remove

- 1) Click "Remove" to pop up a confirmation window. Click "Confirm" to remove and clear the panel data.

